



# Emulators

## Scenarios on error

### Review details problem

Scripts tested OK with NTBR, then integrated into a group, then launched on the probe, crash!

### Solution(s)

Check that the Extra client Environment is set.

To do this, simply run robot properties, choose the probe in question and configure the EC Extra identically configured in the paths of the newtest.ini NTBR, namely:

```
[ACTOR-extra]
PathExeMedium = C: \ Program Files \ Attachmate \ E E2K \
extra.exe!
PathLibMedium = C: \ Program Files \ Attachmate \ E E2K \
ehlap32.dll!
```

In the global preferences of the emulator, check the configuration (eg "A" as the name of the shortcut XXXX.edp session).

## See also